Installing lanseo on MacOS with MAMP

Download & install the necessary software


Installing MAMP

Download MAMP from their site: https://www.mamp.info/en/downloads/


Choose the appropriate version if you're running an Intel processor or Apple Silicon.

Run the installation program. This will install MAMP and a demo version of MAMP Pro. lanseo only needs the functionality in MAMP so you do not need to purchase MAMP Pro unless you want to.

After the installation, you will find a folder called MAMP in the Applications folder. Open this folder by double clicking on it and then start the MAMP application.



Most of the standard values are sufficient for lanseo, but a couple of adjustments need to be done first. Choose **Preferences** and then the **Ports** tab. Click the button "**80 & 3306**" to set MAMP to the default ports for web and MySQL.



Installing lanseo

To install the lanseo software, download the installation files which can be found at https://www.ianseo.net/Releases.php in the zip file for Linux/Mac

Setting up the system

For the purpose of the guide lanseo will be installed in its own folder, called **ianseo**.

- Open folder "/Applications/MAMP/htdocs"
- 2. Create a folder inside it and name it "ianseo" (all lower case, without quotes)
- 3. Uncompress the contents of the downloaded zip file inside the ianseo folder
- 4. IMPORTANT: Open the folder "/Applications/MAMP/htdocs/ianseo/Common" and delete the file **config.inc.php** (if it exists) to allow the installation procedure to start.
- 5. Open a terminal window (Applications -> Utilities -> Terminal)
- 6. Go to the MAMP folder by type the command below, including a space between cd and /, and press Enter:

cd /Applications/MAMP/htdocs


7. Type the following command and press Enter. You will be asked the password of your user: enter it but remember that nothing will be displayed while typing, not even *.

sudo chown -R nobody:admin ianseo

8. Type the following command and press Enter (again it can ask for the password): sudo chmod -R 777 ianseo

Running Ianseo

Start the MAMP application and then press the Start button. This will start the Apache web server and the MySQL database. You may be prompted to enter your password; enter it to continue.



Once MAMP starts, your browser should automatically open to a Welcome to MAMP page showing the current version number.

To start lanseo, enter the address http://localhost/ianseo in a new tab. You will first need to agree to the GPL3 License Agreement. Check the box and click on the *I AGREE* button. Once that is done, you should see a screen similar to the one below showing that the software is installed correctly. Click *Continue* to proceed.

PHP settings php.inifile				
Parameter	Optimal value	System value		
PHP version	5.0	7.4.21		
memory_limit	48M	128M		
max_execution_time	120	30		
post_max_size	16M	8M		
upload_max_filesize	16M	32M		
Loa	ded modules			
Module	Required	Status		
mysqli	installed	installed		
curl	installed	installed		
gd	installed	installed		
mbstring	installed	installed		
iconv	installed	installed		
Although you php.ini file is no IANSEO should perform corre We strongly encourage you to	ctly for most of its fu	inctionality.		
	Continue			

If this is a new installation, follow the onscreen instructions. WARNING: During installation, MAMP does not set the MySQL root password, so when the installer will ask for it, leave it blank. The other fields can be left with default values. Click the *Create user and database* button to proceed. Note: If the installation program displays an error message indicating that it could not connect to the database, enter "root" in the *ADMIN Password to create users and databases* fields and click the *Create user and database* button to try again.

Parameter	Write server	Read server
Host	localhost	
Username	ianseo	
Password	ianseo	
Database name	ianseo	
Data can be written and read in two separate serv provided the read server is a synchronous replica If in doubt leave the right column blank!		
If user and database are to be created from scratc you can provide the password of the ROOT user of WARNING!!! PASSWORDS WILL BE TRANSMITTE OVER THE INTERNET SO IT MIGHT BE WISER	f the servers.	
TO CREATE THE USERS WITH OTHER TOOLS!!!		

Once the database information is configured, you should see the message below. Ianseo is now installed on your system.



Click on the link "*Go to IANSEO!*" to update your system to the latest version. This will automatically download the latest version of the software and update the language files. When this is finished you will see the message "*The upgrade process is finished*.". Click the button to continue.

You should now see the screen below. lanseo is now fully installed and ready to be used!

